FORCE Release 0.5.0

unknown

Sep 28, 2020

CONTENTS

1	User Manual	3
	1.1 Introduction	
	1.2 Installation	3
2	Developer Manual	5
	2.1 FORCE BDSS Design	5
	2.2 Plugin Development	11
	2.3 FORCE Project Developer Guidelines	16
3	API Reference	19
4	Indices and tables	21

This site contains documentation for the Business Decision Support System (BDSS), implemented under the Formulations and Computational Engineering (FORCE) project within Horizon 2020 (NMBP-23-2016/721027).

USER MANUAL

1.1 Introduction

The Business Decision System is the CLI support for the evaluation of Pareto front computations. It is a single executable force_bdss that interprets a workflow specification file, normally generated via the GUI workflow manager.

By itself, the executable and the code implementing it provides no functionality. All functionality comes from external plugins, extending the API to provide new entities, specifically:

- Multi Criteria Optimizer (MCO)
- DataSources, which can be a simulator or just a database
- Notification Listeners, like a remote database which retrieve data during the computation
- UI Hooks, which permit to define additional operations which will be executed at specific moments in the UI lifetime (before and after execution of the BDSS, before saving the workflow)

Plugin support requires compliance to the Force BDSS api for plugins. Extensions are registered via setuptools entry points.

Execution of the force bdss executable is simple. Invoke with:

```
force_bdss workflow.json
```

1.2 Installation

The BDSS, the Workflow Manager and all plugins can be cloned from the Force 2020 github respositories. For the BDSS and Workflow Manager,

```
git clone https://github.com/force-h2020/force-bdss
git clone https://github.com/force-h2020/force-wfmanager
```

1.2.1 Enthought Deployment Manager

The BDSS, the Workflow Manager and plugins must be installed through the Enthought Deployment Manager (EDM), a python virtual environment and package manager. For new users it is worth examining EDM's documentation.

To install EDM, follow the instructions specific to your operating system ,here.

1.2.2 The Bootstrap Environment

Once EDM is installed create a 'bootstrap' environment from which you can install the BDSS, Workflow Manager and plugins,

```
edm install -e bootstrap -y click setuptools
```

Note that 'bootstrap' can be replaced by any name to the same effect. Now you can enter bootstrap with,

edm shell -e bootstrap

and your shell prompt is prefixed with (bootstrap).

1.2.3 The BDSS Runtime Environment

Although repositories (BDSS, etc) are installed *from* the bootstrap environment, they are installed *into* a separate environment, within which the BDSS and the Workflow Manager will actually run. Thus this environment has also to be created before installation. To do this first cd into the cloned force-bdss respository,

~/Force-Project (bootstrap)\$ cd force-bdss

and then,

~/Force-Project/force-bdss (bootstrap)\$ python -m ci build-env

This creates a environment called force-pyXX, where XX refers to the python version that the environment runs (e.g. force-py36 for python 3.6). You will now see it in the list of EDM environments,

```
(bootstrap)$ edm environments list
>> * bootstrap cpython 3.6.9+2 win_x86_64 msvc2015 ~\.edm\envs\bootstrap
>> force-py36 cpython 3.6.9+2 win_x86_64 msvc2015 ~.edm\envs\force-pyXX
```

1.2.4 Repository Installation

From the bootstrap environment (not force-pyXX!), for each respository in turn, cd into its directory and then install it with python -m ci install. i.e.,

```
~/Force-Project/force-bdss (bootstrap)$ python -m ci install
~/Force-Project/force-bdss (bootstrap)$ cd ../force-wfmanager
~/Force-Project/force-wfmanager (bootstrap)$ python -m ci install
...etc
```

DEVELOPER MANUAL

2.1 FORCE BDSS Design

The BDSS is an Envisage/Task application. it uses tasks to manage the plugin system, with stevedore to manage the additions.

2.1.1 Application

The main class is the BDSSApplication, an envisage. Application subclass, which is in charge of loading the plugins, and also adding the relevant core plugins to make the whole system run. Specifically it loads:

- The FactoryRegistryPlugin, which is where all external plugins will put their classes.
- Depending on the -evaluate switch, a relevant execution plugin:
 - OptimizeOperation: Invokes the MCO.
 - EvaluateOperation: performs a single point evaluation, that is, executes the pipeline only once.

Note: the design requiring the --evaluate switch assumed a "Dakota" model of execution (external process controlled by Dakota). In the current Enthought Example plugin we use both the --evaluate strategy and direct control, where all the calculation is performed without spawning additional processes other than the initial force_bdss.

The BDSSApplication contains the following structure:

At the application level, there are three main attributes of type:

- WorkflowFile: contains the Workflow object, as well as the ability to read, write from file
- IOperation: determines the operation that will be performed by the BDSS
- IFactoryRegistry: contains references to all IFactory classes that are contributed by currently installed plugins. This object is constructed from by the BDSSApplication, using the Envisage plugins installed in the local environment, but is actually used by WorkflowReader to instantiate serialised Workflow objects from file.

Upon start up, the ${\tt BDSSApplication}$ performs the following process:

2.1.2 Operations

The IOperation interface defines the requirements for an operation that can be performed by the BDSS. The BaseOperation class provides this interface and contains useful routines that are used to set up both internal and external communication routes. Currently we have 2 subclasses of this base class: EvaluateOperation and OptimizeOperation.

The OptimizeOperation (the default operation performed by the force_bdss) is designed to work alongside a BaseMCO subclass, that defines an optimization method to be performed on a Workflow instance.

The EvaluateOperation (invoked by using the --evaluate flag with the force_bdss command line application) is designed to work alongside a BaseMCOCommunicator subclass that determines how to send and receive MCO parameters and KPIs.

2.1.3 Class Diagrams

Factory Classes

Factories are used in the BDSS to modularise the code and therefore allow additional components to be contributed using plugins.

The BaseFactory class fulfills an IFactory interface, and is therefore able to be contributed and subsequently located by the BaseExtensionPlugin and FactoryRegistryPlugin classes respectively

Each individual BaseFactory subclass also provides an interface that inherits from IFactory.

Model Classes

Each BaseModel class is designed to act as both a serializable and visual representation of a Workflow object. It contains any information that is exposed to the user and, since it inherits from HasTraits, the UI components are provided by the TraitsUI library.

The BaseModel classes all share a common API for serialization, event handling and workflow verification:

- notify (BaseDriverEvent) : Takes an BaseDriverEvent instance and assigns it to the event attribute.
- verify(): Performs a set of checks on the model attributes and returns a list of VerifierError instances describing any issues.
- serialize(): Returns a dictionary object containing basic python values able to be written to file as a JSON.

The BaseModel.verify and BaseModel.serialize methods are expected to be overridden by any subclass to suit the needs of the developer, whereas the BaseModel.notify method is designed to be used as a setter method for the event attribute. Further information is available on both event handling and verification pathways in the BDSS.

Runtime Classes

The factory classes act as creators of BaseModel instances, as well as other objects that are only used during an MCO run. The following sections take a closer look at each of these objects in turn

МСО

The BaseMCOFactory fulfills the IMCOFactory interface. It is able to construct both BaseMCO and BaseMCOModel subclasses and also contains references to a list of objects that fulfill the IMCOParameterFactory interface. Likewise, the BaseMCOParameterFactory provides this interface and constructs BaseMCOParameter subclasses. Consequently, each MCO must declare a set of parameter types that it is able to use.

The BaseMCOModel class provides user input required by a BaseMCO class during runtime. It also contains references to, and methods used to broadcast the MCO-related BaseDriverEvent subclasses: MCOStartEvent, MCOProgressEvent and MCOFinishEvent. The variables designated as KPIs are represented by a list of KPISpecification objects, which also provide scaling instructions in order to convert them into comparable unit-less values. The BaseMCO class' only job is to provide the the implementation of any optimization algorithm that will be performed during the BaseMCO.run method. This method takes in one argument, which must fulfill the IEvaluator interface.

Any object that provides this interface must contain a reference to the corresponding <code>BaseMCOModel</code>, as well as an implementation of an <code>IEvaluator.evaluate</code> method which is used to return the state of the system to be optimized for a given list of input parameters. It is therefore expected that the <code>BaseMCO.run</code> method will perform some iteration over <code>IEvaluate.evaluate</code>, passing in possible MCO parameter values and obtaining the corresponding KPI values as output.

Data Sources

The BaseDataSourceFactory fulfills the IDataSourceFactory interface. It is able to construct both BaseDataSource and BaseDataSourceModel subclasses.

The BaseDataSourceModel class provides user input required by a BaseDataSource class during runtime. It is also used in the backend to broadcast any Data Source-related events: DataSourceStartEvent and DataSourceProgressEvent and DataSourceFinishEvent.

The BaseDataSource class has methods that require implementation: BaseDataSource.run and BaseDataSource.slots The run method contains a black box of code that will be performed during evaluation of the workflow. It expects a reference to the BaseDataSourceModel as well as a list of DataValue instances that contain extra parameters generated during runtime. The slots method is used to communicate the expected length and format of both the input and output lists of DataValues associated with the run method, mainly so that this can be displayed in the UI before an MCO run is called.

Notification Listeners

The BaseNotificationListenerFactory fulfills the INotificationListenerFactory interface. It is able to construct both BaseNotificationListener and BaseNotificationListenerModel subclasses

The BaseNotificationListenerModel class provides user input required by a BaseNotificationListener class during runtime.

2.1.4 Workflow

The Workflow contains a full description of the system to be optimised, the optimisation procedure and any listener objects that are expected to react on events that are created during runtime.

Workflow Specification

The "Workflow" object of the application needs to contain a representation of three entities:

- Multi Criteria Optimizer (MCO)
- Data Sources
- Notification Listeners

Additionally, messages can be sent and received between the CLI force_bdss application and the force_wfmanager GUI via a subset of notification listener, known as a 'UI Hook'.

There are a few core assumptions about each of these entities:

- The MCO provides numerical values and injects them into a pipeline made of multiple layers. Each layer is composed of multiple Data Sources. The MCO can execute this pipeline directly, or indirectly by invoking the force_bdss with the option --evaluate. This invocation will produce, given a vector in the input space, a vector in the output space.
- The Data Sources are entities that are arranged in layers. Each Data Source has inputs and outputs, called slots. These slots may depend on the configuration options of the specific data source. The pipeline is created by binding data sources outputs on the layers above with the data sources inputs of a given layer. Each output can be designated as a KPI and thus be transmitted back to the MCO for optimization.
- A Notification Listener listens to the state of the MCO (i.e. Started/New step of the computation/Finished) and can perform tasks accordingly. For example, it could connect to a remote database which is filled with the MCO results during the computation (e.g. the GUI force_wfmanager has a notification listener in order to fill the result table).
- UI Hooks permit to define additional operations which will be executed at specific moments in the UI lifetime (before and after execution of the BDSS, before saving the workflow). Those operations won't be executed by the command line interface of the BDSS.

Workflow Class

The specifications above can be performed by the Workflow class, a concrete implementation of a pipeline for the BDSS:

- The Workflow.mco_model attribute refers to a BaseMCOModel instance that defines user-inputted parameters for the MCO. It contains a list of BaseMCOParameter instances that define the search space, as well as a list of KPISpecification instances referring to variables that will be optimised. It also defined the types of MCOStartEvent, MCOProgressEvent and MCOFinishEvent classes that will be emitted during the MCO run time.
- The Workflow.execution_layers attribute contains a list of ExecutionLayer instances that represent each Data Source layer. Within each element, the ExecutionLayer.data_sources attribute contains a list of BaseDataSourceModel instances that define the input and output slots for each Data Source. The ExecutionLayer.execute_layer method can be called to calculate all DataValue objects that are generated by that layer.
- The Workflow.notification_listeners attribute contains a list of BaseNotificationListener instances that define user-inputted parameters for each notification listener that will be active during the MCO run.

During an Force BDSS run, the Workflow object is used to initialise the MCO and also perform each calculation of the system state for a given set of input parameter values. This is carried out by the following steps:

- 1. Pass the Workflow instance into the BaseMCO.run method as the evaluator argument.
- 2. For every iteration in the MCO method, Workflow.evaluate method can then be invoked for a list of values referring to the state of each BaseMCOParameter. The return values represent the corresponding state of each KPISpecification.
- 3. Both parameter and KPI values can then be broadcast to any BaseNotificationListener instances active using the Workflow.mco_model.notify_progress_event method.
- 4. Iterate steps 2 and 3 until all evaluations have been performed and the MCO has finished.

Workflow JSON Files

A Workflow object can be instantiated from an appropriately formatted workflow JSON file. Typically the structure of this JSON represents a serialised version of each object contained within the Workflow. Currently the WorkflowReader supports two file versions: 1 and 1.1. There are only minor differences between both versions:

- 1. Workflow.mco_model attribute data stored under mco key in version 1 vs mco_model key in 1.1
- 2. Workflow.execution_layers attribute data represented as a list of lists in version 1 vs a list of dictionaries in version 1.1. In version 1, each element in the outer list implicitly represents an execution layer, whilst each element in the the inner list represents the serialised status of a DataSourceModel instance. In version 1.1, we explicitly include the status of each ExecutionLayer instance in the outer list, and therefore each dictionary element is also expected to contain a data_sources key with a list of DataSourceModel statuses.

The WorkflowWriter will produce JSON files that conform to the latest available version (currently 1.1) by default.

2.1.5 Event Handling

The BaseDriverEvent class is the main object used to relay messages internally between components of the BDSSApplication. It can also be serialized in order to be passed between external programs (i.e. the force_wfmanager) as a JSON.

Any events that are created during runtime are propagated through the Workflow object hierarchy, up to the BaseOperation class that is being performed by the BDSSApplication, before finally being broadcast to all BaseNotificationListener classes present. Consequently, the BaseModel class contains an event attribute, as well as a notify method that is used to set it. Listeners can then detect changes in any BaseModel. event subclass, and process the new event accordingly.

Any actions that are required to be performed upon notification of a specific <code>BaseDriverEvent</code> subclass are handled by the <code>BaseNotificationListener.deliver</code> method.

In this way, we can also use <code>BaseDriverEvents</code> to control the progress of an MCO run, since after every broadcast, the <code>OptimizeOperation</code> checks its run time status to see whether the event has triggered a MCO 'pause' or 'stop' signal.

Additionally, the BaseDataSource._run method shadows the BaseDataSource.run method in order to signal the beginning and end of a data source execution. By doing so, we are able to pause and stop and MCO run between each run method invocation, which represents a black box operation.

2.1.6 Verification

Any Workflow instance can be verified by invoking the verify_workflow function. This returns a list of VerifierError instances, generated by iterating through the Workflow hierarchy and calling each bound verify method in turn.

In the BDSSApplication, this function is called during the beginning of both OptimizeOperation.run and EvaluateOperation.run methods. If any VerifierError instances are returned, then an Exception is raised and the program will terminate. Additionally, since the Workflow can be verified prior to the force_bdss runtime, the force_wfmanager GUI is able to report any errors back to the user as the Workflow is being constructed.

2.1.7 Package Structure

As well as a command line program, the BDSS also comes with a force_bdss package containing objects required by plugin developers. These should be publicly accessed through the force_bdss.api module, but a brief explanation of the internal structure is provided below.

The data_sources, mco, notification_listeners and ui_hooks packages, and the base_extension_plugin class, contain all the base classes that plugin developers need to use in order to write a plugin. They have been coded to be as error tolerant as possible, and deliver robust error messages as much as possible. Further information regarding these classes can be found in the plugin development documentation

The io package contains the reader and writer for the model. It simply serializes the model objects and dumps them to JSON, or vice-versa. Note that the reader requires the factory registry, because you can't load entities from the file if you don't have the appropriate plugin, as only the plugin knows the model structure and can therefore take the JSON content and apply it to the model object.

The core_plugins contains fundamental plugins that are considered part of a "standard library", providing common data sources, MCOs and other relevant objects. Finally, core contains:

- base classes for a few entities that are reused for the plugins.
- the DataValue entity. This is the "exchange entity" between data sources. It is a value that also contains the type, the accuracy, and so on. It can refer to anything: a float, an array, a string, etc.
- Workflow model object, representing the entire state of the BDSS.
- input/output_slot_info contain the _bound_ information for slots. A DataSource provides slots (see slot module) but these are not bound to a specific "variable name". The SlotInfo classes provide this binding.
- execution_layer contains the ExecutionLayer class, which provides the actual machinery that runs the pipeline.
- verifier contains a verification function that checks if the workflow can run or has errors.

2.1.8 Future directions

The future design will probably need to address the following:

- Check if the --evaluate strategy and design is still relevant. More MCOs are needed for reasonable conclusions.
- IWM is going to provide a strict description of types (osp-core, previously known as simphony). Currently, all type entries in the e.g. slots are simple strings as a workaround. This is supposed to change once IWM provides a comprehensive set of types.
- The project is now at a stage where plugins can be developed, and real evaluations can be performed. We can solve the current toy cases, but real cases and UI requirements may promote the need for additional requirements.

2.2 Plugin Development

Force BDSS is extensible through plugins. A plugin can be (and generally is) provided as a separate python package that makes available some new classes. Force BDSS will find these classes from the plugin at startup.

A single Plugin can provide one or more of the following entities: MCO, DataSources, NotificationListeners, UIHooks. It can optionally provide DataViews to be used by the force_wfmanager GUI.

An example plugin implementation is available at:

https://github.com/force-h2020/force-bdss-plugin-enthought-example

To implement a new plugin, you must define at least four classes:

- The Plugin class itself.
- One of the entities you want to implement: a DataSource, NotificationListener, MCO, or UIHook.
- A Factory class for the entity above: it is responsible for creating the specific entity, for example, a DataSource
- A Model class which contains configuration options for the entity. For example, it can contain login and password information so that its data source knows how to connect to a service. The Model is also shown visually in the force_wfmanager UI, so some visual aspects need to be configured as well.

The plugin is made available by having it defined in the setup.py file entry_points section, under the namespace force.bdss.extensions. For example:

```
entry_points={
    "force.bdss.extensions": [
        "enthought_example = "
        "enthought_example.example_plugin:ExamplePlugin",
    ]
}
```

2.2.1 The plugin

The plugin class must be

- Inheriting from force_bdss.api.BaseExtensionPlugin
- Implement a id class member, that must be set to the result of calling the function plugin_id(). For example:

```
id = plugin_id("enthought", "example", 0)
```

- Implement a method get_factory_classes() returning a list of all the classes (NOT the instances) of the entities you want to export.
- Implement the methods get_name(), get_version() and get_description() to return appropriate values. The get_version() method in particular should return the same value as in the id (in this case zero). It is advised to extract this value in a global, module level constant.

2.2.2 The Factory

The factory must inherit from the appropriate factory for the given type. For example, to create a DataSource, the factory must inherit from BaseDataSourceFactory. It then needs these methods to be redefined

- get_identifier(): must returns a unique string, e.g. a unid or a memorable string that must be unique across your plugins, present and future.
- get_name(): a memorable, user presentable name for the data source.
- get_description(): a user presentable description.
- get_model_class(): Must return the Model class.
- get_data_source_class(): Must return the data source class.

2.2.3 The Model class

The model class must inherit from the appropriate Base model class, depending on the entity, for example BaseDataSourceModel in case of a data source.

This class then must be treated as a Traits class, where you can use traits to define the type of data it holds. Pay particular attention to those data that can modify the slots. For those, add a changes_slots=True metadata tag to the trait. This will notify the UI that the new slots need to be recomputed and presented to the user. Failing to do so will have unexpected consequences. Example:

```
class MyModel(BaseDataSourceModel):
    normal_option = String()
    option_changing_slots = String(changes_slots=True)
```

Typically, options that change slots are those options that modify the behavior of the computational engine, thus requiring more or less input (input slots) or producing more or less output (output slots).

Many BaseModel subclasses also include a verify method, which is called before an MCO run starts to ensure that the execution will be successful. This verification step can also be triggered in the WfManager UI even before an MCO run is submitted. For BaseDataSourceModel subclasses it is automatically performed whenever the slots objects are updated, however developers can also include the verify=True metadata on any additional trait that requires verification. Including this in example above:

```
class MyModel(BaseDataSourceModel):
    normal_option = String(verify=True)
    option_changing_slots = String(changes_slots=True)
```

You can also define a UI view with traitsui (import traitsui.api). This is recommended as the default view arranges the options in random order. To do so, have a default_traits_view() method:

```
def default_traits_view():
    return View(
        Item("normal_option"),
        Item("option_changing_slots")
)
```

2.2.4 The DataSource class

This is the "business end" of the data source, and where things are done. The class must be derived from BaseDataSource), and reimplement the appropriate methods:

- run(): where the actual computation takes place, given the configuration options specified in the model (which is received as an argument). It is strongly advised that the run() method is stateless.
- slots(): must return a 2-tuple of tuples. Each tuple contains instances of the Slot class. Slots are the input and output entities of the data source. Given that this information depends on the configuration options, slots() accepts the model and must return the appropriate values according to the model options.

2.2.5 The MCO class

Like the data source, the MCO needs a model (derived from BaseMCOModel), a factory (derived from BaseMCOFactory) and a MCO class (derived from BaseMCO). Additional entities must be also provided:

- MCOCommunicator: this class is responsible for handling communication between the MCO and the spawned
 process when the MCO is using a "subprocess" model, that is, the MCO invokes the force_bdss in evaluation
 mode to compute a single point.
- parameters: We assume that different MCOs can support different parameter types for the generated variables. Currently, only the "range" type is commonly handled.

The factory then must be added to the plugin get_factory_classes() list.

The factory must define the following methods:

```
def get_identifier(self):
def get_name(self):
def get_description(self):
def get_model_class(self):
```

as in data source factory. The following:

```
def get_optimizer_class(self):
def get_communicator_class(self):
```

Must return classes of the MCO and the MCOCommunicator. Finally:

```
def get_parameter_factory_classes(self):
```

Must return a list of classes of the parameter factories.

Optimizer Engines

The force_bdss.api package offers the BaseOptimizerEngine and SpaceSampler abstract classes, both of which are designed as utility objects for backend developers.

The BaseOptimizerEngine class provides a schema that can easily be reimplemented to act as an interface between the BDSS and an external optimization library. Although it is not strictly required to run an MCO, it is expected that a developer would import the object into a BaseMCO.run implementation, whilst providing any relevant pre and post processing of information for the specific used case that the MCO is solving. The base class must simply define the following method:

def optimize(self):

Which is expected to act as a generator, yielding values corresponding to optimised input parameters and their corresponding KPIs. A concrete implementation of this base class, the WeightedOptimizerEngine, is provided that uses the SciPy library as a backend.

The SpaceSampler abstract class also acts as a utility class in order to sample vectors of values from a given distribution. Implementations of this class could be used to either provide trial parameter sets to feed into an optimiser as initial points, or importance weights to apply to each KPI. The base class must define the following methods:

```
def _get_sample_point(self):
def generate_space_sample(self, *args, **kwargs):
```

Two concrete implementations of this class are provided: UniformSpaceSampler, which performs a grid search and DirichletSpaceSampler, which samples random points from the Dirichlet distribution.

2.2.6 MCO Communicator

The MCO Communicator must reimplement BaseMCOCommunicator and two methods: $receive_from_mco()$ and $send_to_mco()$. These two methods can use files, stdin/stdout or any other trick to send and receive data between the MCO and the BDSS running as a subprocess of the MCO to evaluate a single point.

2.2.7 Parameter factories

MCO parameter types also require a model and a factory per each type. Right now, the only typo encountered is Range, but others may be provided in the future, by MCOs that support them.

The parameter factory must inherit from BaseMCOParameterFactory and reimplement:

```
def get_identifier(self):
def get_name(self):
def get_description(self):
```

as in the case of data source. Then:

def get_model_class(self):

must return a model class for the given parameter, inheriting from BaseMCOParameter. This model contains the data the user can set, and is relevant to the given parameter. For example, in the case of a Range, it might specify the min and max value, as well as the starting value.

2.2.8 Notification Listeners

Notification listeners are used to notify the state of the MCO to external listeners, including the data that is obtained by the MCO as it performs the evaluation. Communication to databases (for writing) and CSV/HDF5 writers are notification listeners.

The notification listener requires a model (inherit from BaseNotificationListenerModel), a factory (from BaseNotificationListenerFactory) and a notification listener (from BaseNotificationListener). The factory requires, in addition to:

```
def get_identifier(self):
  def get_name(self):
  def get_description(self):
  def get_model_class(self):
```

the method:

```
get_listener_class()
  return the notification listener object class.
```

The NotificationListener class must reimplement the following methods, that are invoked in specific lifetime events of the BDSS:

```
def initialize(self):
    Called once, when the BDSS is initialized. For example, to setup the
    connection to a database, or open a file.
def finalize(self):
    Called once, when the BDSS is finalized. For example, to close the
    connection to a database, or close a file.
def deliver(self, event):
    Called every time the MCO generates an event. The event will be passed
    as an argument. Depending on the argument, the listener implements
    appropriate action. The available events are in the api module.
```

2.2.9 UI Hooks

UI Hooks are callbacks that are triggered at some events during the lifetime of the UI. It has no model. The factory must inherit from BaseUIHooksFactory, and must reimplement get_ui_hooks_manager_class() to return a class inheriting from BaseUIHooksManager. This class has specific methods to be reimplemented to perform operations before and after some UI operations.

Any BaseDriverEvents that are required to be delivered to a UI can be indicated using the UIEventMixin class. The MCOStartEvent, MCOProgressEvent and MCOFinishEvent are all examples of such objects.

2.2.10 Envisage Service Offers

A plugin can also define one or more custom visualization classes for the GUI application <code>force-wfmanager</code>, typically to either display data or provide a tailor-made UI for a specific user. In which case, the plugin class must inherit from <code>force_bdss.core_plugins.service_offer_plugin.ServiceOfferExtensionPlugin</code> , which is a child class of <code>BaseExtensionPlugin</code>. Any UI subclasses can then be made discoverable by <code>force-wfmanager</code> using the <code>envisage ServiceOffer protocol</code> through the <code>get_service_offer_factories</code> method:

```
def get_service_offer_factories(self):
    """A method returning a list user-made objects to be provided by this
    plugin as envisage ServiceOffer objects. Each item in the outer list is
    a tuple containing an Interface trait to be used as the ServiceOffer
    protocol and an inner list of subclass factories to be instantiated
    from said protocol.
    Returns
    ______
    service_offer_factories: list of tuples
    List of objects to load, where each tuple takes the form
    (Interface, [HasTraits1, HasTraits2..]), defining a Traits
    Interface subclass and a list of HasTraits subclasses to be
    instantiated as an envisage ServiceOffer.
    """
```

Make sure to import the module containing the data view class from inside get_service_offer_factories: this ensures that running BDSS without a GUI application doesn't import the graphical stack.

Custom UI classes

There are currently two types of custom UI object that may be contributed by a plugin: IBasePlot and IContributedUI. These interfaces represent requirements for any UI feature that can be used to display MCO data or a present a simplified workflow builder respectively.

Also, multiple types of plugin contributed UI objects can be imported in the same call. For instance:

```
def get_service_offer_factories(self):
    from force_wfmanager.ui import IBasePlot, IContributedUI
    from .example_custom_uis import PlotUI, ExperimentUI, AnalysisUI
    return [
        (IBasePlot, [PlotUI]),
        (IContributedUI, [ExperimentUI, AnalysisUI])
]
```

2.3 FORCE Project Developer Guidelines

When contributing to the FORCE project, please clone the relevant Git repository and perform all suggested changes on a new branch (there is no need to fork the repository). Some general guidelines are provided below.

2.3.1 Continuous Integration

The FORCE project uses a TravisCI runner that will build and test any code pushed to a GitHub repository. These CI checks can also be performed locally whilst developing.

Mandatory Checks

1) Contribute unit tests for any fixes or new features using the unittest library. Each module should contain a test/ folder with python files contributing unittest.TestCase objects. You can run (from an edm environment) the following command to perform all unit tests within a repository:

```
python -m ci test
```

All tests must pass in order for a pull request to be accepted.

2) Use Flake8 style guidelines for new code. These can be tested by running:

```
python -m ci flake8
```

Note: If you enforce stricter style guidelines (such as Black), then this is fine as long as they also pass the Flake8 test.

Optional Checks

4) Some FORCE projects will also build Sphinx documentation as part of the CI. If this is failing for any reason, you can run the following command to debug locally:

python -m ci docs

5) Some FORCE projects have thresholds for code coverage that must be met when contributing new code. These will be defined within a coverage.yml file in the repository top-level directory. You can check the coverage by running:

python -m ci coverage

Note: when performing this command locally, the final step will attempt to upload the report to Codecov, which will fail unless an appropriate token is present. This is unnecessary to simply view the coverage report and can be safely ignored.

2.3.2 Pull Request Review

When the CI tests are passing locally, push the branch to origin using:

git push --set-upstream origin <branch-name>

And create a GitHub pull request describing the changes made and the context for doing so by following the pull request template provided. Some repositories are protected and will explicitly require at least one reviewer for a pull request to be merged. However, we strongly request that ANY code is reviewed before merging.

When reviewing, try to ensure that the PR creator remains the only committer to the PR branch. A reviewer can make a new PR against the PR branch if they want to suggest extensive changes.

THREE

API REFERENCE

FOUR

INDICES AND TABLES

- genindex
- modindex
- search